



# SPE


## Systems – Common Mistakes – Tools

Renato Lo Cigno


<http://disi.unitn.it/locigno/teaching-duties/spe>

- What is a system?
- Common mistakes in PE
- PE tools
  - Measures
  - Simulations
  - Analysis


- A “system” is any physical or logical ensemble of which we want to measure some metrics
- Normally we wish to predict some “output” given some “input”




- We are given a “web server”
- Evaluate the service “responsiveness”
- Inputs = queries  $q_i$
- Output = answer delays  $d_i$



- How do we define a “web server”, what is the goal of our evaluation
  - Hardware?
  - Software?
  - What are the “measurement points” of a web server?
- Is a delay a good measure of responsiveness?
- What are the queries  $q_i$  that are meaningful for the evaluation?
- What is the “correct” sequence of queries
  - In PE this is normally called the “workload” of the system under evaluation and its choice is of the utmost importance




- What is a “web server”?  
– (Answer) or Model 1




**good for the user!**

- What is a “web server”?
  - Model 1 bis




**good for the ISP or  
network manager  
(your PC is not my business)!**

- What is a “web server”?
  - Model 2




**good for a data centre  
or a CDN!**

- What is a “web server”?
  - Model 3




- What is a “web server”?
  - Model 4



good for the software developer!

- What is a “web server”?
  - Model 5



**good for you!!**



- Different models may require different evaluation tools or techniques
  - Model 1 (specially 1bis) can be easily measured if you seek a “local” answer, but measuring “on average” can simply be impossible
  - Models 2 and 3 can be also easily measured
    - but measures do not give “what-if” answers, so they are not good for design
  - Model 4 is very difficult to measure
- All models can be simulated, but we need to design the simulator correctly
- Some models are prone to analytical solutions, which are fast and easy, but can be very “rough”
  - Very useful to “dimension” systems

- The workload
  - $q_1 \rightarrow d_1 ; q_2 \rightarrow d_2 ; q_3 \rightarrow d_3 ; q_4 \rightarrow d_4 ; \dots$
  - Is it meaningful?
  - Is it representative of all real situations?
- Queries are not isolated and arrive with temporal relationships
  - $Q = \{q_1, t_1; q_2, t_2; q_3, t_3; q_4, t_4; \dots\}; q_i \text{ in } \mathbf{q}; t_i \text{ in } \mathbf{R}^+ \text{ or } \mathbf{Z}$
  - where  $\mathbf{q}$  is the set of all possible queries
  - $\mathbf{R}^+$  and  $\mathbf{Z}$  are real or natural numbers (including zero) depending on time being continuous or discrete

- The workload
- Does the sequence and temporal distribution of the workload influence results?
  - $Q = \{q_1, t_1; q_2, t_2; q_3, t_3; q_4, t_4; \dots\} \rightarrow \{d_1; d_2; d_3; d_4; \dots\}$
  - imply that
  - $Q = \{q_3, t_1; q_2, t_2; q_1, t_3; q_4, t_4; \dots\} \rightarrow \{d_3; d_2; d_1; d_4; \dots\}$
  - **or not??**
- The workload is often called also the “**arrival process**” to the system
- Notice that the PE output is normally NOT the output / service of the system
  - A web server does not yield “delays” it returns web pages!!



- The output: responsiveness
  - What delay are we measuring?
  - Model 1: is the time needed for transmission and for the browser rendering meaningful?
  - Model 4: Database interactions of a CMS is our business?
  - Model 2: If  $q_i$  requires back-end computation (e.g., Hadoop), is that to be included or separated?
  - Model 4: Where do you put the probes to measure in-OS performance?



- Projects often fails due to PE analysis failures
  - The system designed does not perform as it should
  - The software project lags way behind schedule
    - Components have not been analysed
    - The development cycle has not been analysed
  - The nuclear reactor explodes when it should not (Chernobil, Fukushima, Three Mile Islands, Superphoenis, ...)
    - The system reliability has not been properly included in PE (TMI)
    - The system dependability has not been included at all (Fukushima)
- PE Analysis often fails due to initial conceptual mistakes



- AKA lack of problem understanding
- Without a model we measure a black-box, not a system
- The measures taken may answer “what”, but never “how” and “why”
- Artificial Intelligence & Machine Learning try to do some analysis on black-boxes
  - They have sophisticated stochastic models behind them
  - The results remains valid until the stochastic model behind is valid
    - e.g., the model assumes that the output distribution has a single mode, if not true the results are not valid



- ***“All Models are Wrong ... some of them are Useful”***  
(Mark Twaine, Albert Einstein, George Box or somebody else much more famous than me)
- ***Alternative version 1: “All Models are Right ... most of them are Useless”***  
(Unknown, reported by T. Tarpey in a seminar in 2009)
- ***Alternative version 2: “All Predictions are correct ... Unless they regard the Future”***  
(maybe Mark Twaine, if not, myself)



- Frequent mistakes in Science & Engineering
  - I want to show that my system is better than yours
  - My boss will fire me if I show that his idea is bogus
- Always present in brochures & commercial datasheets
  - Those are ads, not science
- More often simply lack of pre-analysis
  - I have not given the problem enough time, so my global understanding is not enough to drive the PE process
- Pre-concepts prevent seeing the truth
  - I expect a red ball, and never see the green cube popping out



- I don't know what I need to measure/model
  - Measures taken cannot be interpreted
  - The model I make finally yields no meaningful outputs
    - e.g., results are always constant even changing parameters
- I have a model, but change parameters at random
  - Results taken in this way do not offer insights
- I have so many variables and parameters that the search space is practically infinite
  - Any amount of results will always be negligible w.r.t. to space to be analysed
  - Typical mistake in simulations



- Selection of the correct tool (measures, simulations, analysis) is fundamental
  - e.g., we cannot “measure” a disaster, it’s too late!
  - More later on
- The model must be tailored for the problem
  - Too much details makes it cumbersome & awkward to use
  - Too few details makes results unreliable




- Outputs depends on the inputs
  - A different input than “thought” leads to wrong interpretations
- Biased workload
  - a skewed random generator
  - a workload that include rare events that never happen during the simulation/measure ... yet they are possible
- Changing one parameter of the workload (e.g., adding new web queries) changes also other parameters that are not controlled (e.g., interaction with data-bases)
  - Also, changing variability I also change the mean ...



- Outliers (results that are discarded as not meaningful) must always be checked
  - Instrument fault?
  - “Unlucky” Simulation?
  - Or a mistake in the model/implementation?
- Events that should not happen **must not** be ignored
  - Symptoms of a different system behaviour in measures
  - Symptoms of “eisenbugs” in software (simulations)
  - Symptoms of numerical problems in analytical solutions
  - ...

- This is a “variation” of Impossibles & Outliers
- When building the model some important factor is left out
  - Result change when they should not (the “factor” has changed, but we ignore it)
  - We trust our results ... but they are wrong
- E.g., we model a web-server as a single process, while indeed it is multi-threaded with threads added based on a performance threshold





- If two models give the same output the simpler is preferred
- If a model has more than 100 parameters you can obtain any result you want ...
  - This becomes PE as “Parameters Engineering” not as “Performance Evaluation”
- An esoteric explanation is often appealing, but not necessarily the the correct one


- The model is never put in discussion ... but sometimes it is wrong
- Rutherford vs Thomson Atom is the perfect example
  - The interpretation of scattering was simply impossible with Thomson model

Thomson model


J.J. Thomson's picture of the atom

"corpuscles" (electrons)

"..sphere of uniform positive electrification .."



Rutherford model





© 2012 Encyclopædia Britannica, Inc.

- Stationarity is the property of not changing the behaviour in time:

$$G(t) \approx G(t-t_0) \text{ for all } t_0$$

where  $\approx$  indicates a stochastic equivalent behaviour

- Not all systems and phenomena are stationary
  - Interpreting non-stationary systems in light of a stationary model is wrong





- Assumptions and approximations must be very clear (and declared!!)
  - A PE exercise can be OK if I know its goals and validity, but can be rejected entirely if I think it is about the real system
  - E.g., a multi-core CPU approximated as a single core one
- Results presentation is fundamental
  - Graphs are better than tables & numbers
  - Results must be presented with their confidence
  - The results selected for presentation must:
    - Give insight
    - Enable decisions



- The most traditional “scientific experiment”
- The system must be available, accessible and observable
- Workload generation is fundamental and often difficult
  - E.g., loading a 100Gbit/s optical link
- Changing system parameters can be difficult (impossible sometimes)
- Setting probes to take measures might be difficult (impossible sometimes)
  - E.g., adding a hardware counter to a CPU
- Measures must be repeated to achieve confidence



- They are often considered the most reliable PE form
  - But they do not give predictions!
  - You cannot “measure” disasters, you must avoid them!!
- Measures are intrinsically affected by noise
  - Can be additive, multiplicative, or even distortive
  - In any case it is represented by RVs
- Metrics themselves can be stochastic in nature
  - E.g., replication speed of cells; equilibriums in chemicals at high temperature; completion times of jobs in loaded systems; delays in the Internet; ...



- A software that mimics the behaviour of the system
- Requires an abstract model
- State parameters of the system must be carefully selected

$$S(t) = \{s_1, s_2, \dots, s_N\}$$

- Parameter ranges are important and must be checked
- $t$  is inherently discrete:  $t$  in  $\mathbf{Z}$
- The evolution of the system is described as conditional random variables

$$S(t+1) = V | S(t)$$

where  $V$  is a vector of stationary R.V.



- Workload generation is easier than in measures
- Parametric studies are normally easy
  - But they have a large computational cost
- A simulation “run” is a random walk in the state space of the model
- Simulation runs can be interpreted as Monte Carlo solutions of the set of coupled differential equations that describe the state evolution
- Multiple runs (or batch means techniques) are needed to evaluate the confidence of results



- Finding the model is difficult
- Finding its solution sometimes even more
  - Numerical solutions are often possible
  - Monte Carlo numerical analysis is normally feasible
    - In this case the analysis becomes hybrid with simulations, but the confidence is normally easier to estimate and sometimes it does not require multiple solutions
- Parametric studies are very simple and effective
- Analytical models are often in the form of dynamic equations
  - e.g., coupled differential equations



$$\left\{ \begin{array}{ll} dG(t)/dt = aF(t) & G(0) = G_0 \\ dF(t)/dt = -bG(t) & F(0) = F_0 \end{array} \right.$$

- A set of coupled differential equations
- This example can describe the evolution of a population  $G$  as a function of resources availability  $F$ , which in turn decreases as the population  $G$  increases
  - Is there an equilibrium?
  - If  $G$  represents a bacteria population of animals, or you choose it, will they survive or get extinct

- Measures confirmed with simulations or analysis
  - Insight & Results interpretation
- Analysis confirmed by simulations
  - Be careful not to use the same model!
- Analysis confirmed & tuned with measures
- Simulations confirmed and tuned with measures
- Simulations confirmed by analysis
  
- Never trust a single tool for PE (if possible)



# Tool selection & Tradeoff

Criterion/Metric	Measure	Simulation	Analysis
Stage of design	Prototype – Operational	Any	Any – Very Early
Time required	Variable – Long	Variable	Small
Design complexity	High	Low – Medium	Variable
Accuracy	Variable	Variable	Variable
What-If evaluation	Difficult	Computationally expensive	Easy
Cost	Very High	Low to Medium	Low
Interpretation	Difficult	Medium	Easy
Marketing	Easy	Medium	Difficult (lack of understanding)